

## Settings for printing from application with limited user rights

# PosterJet® 7

### Security settings under Windows

If you do not obtain the necessary permissions, you may have problems during printing from application. To print properly from applications some settings have to be performed. These settings can only be done by the administrator of the respective computer.

Please make sure that you are logged as administrator (full access) on the computer that runs the PosterJet 7 server before you start working on the security settings.

#### Important

This support document examines exclusively common settings of Microsoft Windows. It is highly recommended that you are familiar to the handling of permissions, restrictions and security settings under Windows.

### Security settings in the registry

Necessary effective permissions for the following registry key

My Computer\HKEY\_LOCAL\_MACHINE\SOFTWARE\Eisfeld Datentechnik\Spooler

- Query Value
- Set Value
- Create Subkey
- Enumerate Subkeys
- Notify
- Delete
- Read Control

The above-named permissions correspond to the Windows user group "Power Users".

### Security settings for the Spool folder

Necessary effective permissions for the Spool folder

- Traverse Folder / Execute File
- List Folder / Read Data
- Read Attributes

- Read Extended Attributes
- Create File / Write Data
- Create Folders / Append Data
- Write Attributes
- Write Extended Attributes
- Delete
- Read Permissions

## **Permissions for the shared printers**

Please make sure, that all printers that should be accessible in the network are properly shared.

Necessary effective permissions for the shared printer.

- Print
- Manage printers
- manage Documents
- Read Permissions
- Change Permissions
- Take Ownership